

Use this guide to setup up Sharp Imagers to scan to FTP on Macs

Note: Scan to FTP on Macs is not officially supported by Sharp

- 1. Enter the <u>IP address of your Sharp</u> in the address bar of a web browser.
- 2. Click Address Book (Newer/ & tablet style models).


Continue on page 3 if your Sharp model ends with 10, 11, 40 (ex. MX-2610, MX-5111, MX-5140).


Continue on page 4 for all other MX series MFPs with the newer style web interface.

Click Destination (older style models).

3. Older models only - Login: admin/Sharp (both case sensitive). Click Log in. Continue on page 5.

### Web interface of newer & tablet style Sharps






- 1. Click Add
- 2. Click FTP
- 3. Enter the Address Name (This will be the display name at the MFP).
- 4. Enter the IP address of the Mac to scan to (see page 6).
- 5. Enter the Directory path. The following is recommended: Desktop/Scans

Note: Be sure to create a folder on the Mac desktop and call it: Scans



- 6. Enter the name of the Mac user
- 7. Enter the password of the Mac user
- 8. Check the Set as Default used box

# Configure the Sharp to scan to FTP (tablet style interface)



3 9. Click Submit

### Configure the Sharp to scan to FTP (newer style web interface)

- 1. Select FTP from the Address Type drop-down menu.
- 2. Enter the Address Name (This will be the display name at the MFP).
- 3. Enter the IP address of the Mac to scan to. See page 6 to determine the IP address
- 4. Enter the Directory path. The following is recommended: Desktop/Scans


**Note:** Be sure to create a folder on the Mac desktop and call it: Scans

Seams

- 5. Enter the name of the Mac user
- 6. Enter the password of the Mac user

Note: This is case sensitive and is required

7. Click the Submit button when finished



#### Configure the Sharp to scan to FTP (older style web interface)




- 1. Click the FTP link
- 2. Enter the Address Name (This will be the display name at the MFP).
- 3. Enter the IP address of the Mac to scan to. See page 6 to determine the IP address
- 4. Enter the name of the Mac user
- 5. Enter the password of the Mac user
- 6. Enter the Directory path. The following is recommended: Desktop/Scans

Note: Be sure to create a folder on the Mac desktop and call it: Scans


Seams

7. Click the Submit button when finished




### Obtain the IP address of your Mac











## Enable FTP services (Mac 10.5, 10.6 & 10.7)

